## **MSU Extension Publication Archive**

Archive copy of publication, do not use for current recommendations. Up-to-date information about many topics can be obtained from your local Extension office.

Managing Pesticides on Soybeans to Avoid Contaminating Water Michigan State University Cooperative Extension Service Water Quality Extension Publications Karen A. Renner, Crop and Soil Sciences; Larry G. Olsen, Joy N. Landis, Pesticide Education May 1990 2 pages

The PDF file was provided courtesy of the Michigan State University Library

### Scroll down to view the publication.

# ANAGING PESTICIDES ON SOYBEANS TO AVOID CONTAMINATING WATER

Karen A. Renner Crop & Soil Sciences

Larry G. Olsen Joy N. Landis Pesticide Education

When selecting pesticides for use on soybeans, use the information on this fact sheet to select an appropriate pesticide that is least likely to contaminate surface or groundwater. Lakes, rivers, streams, and other surface water are a critical resource that must be protected by everyone. Many people who live in rural Michigan supply their homes with water from wells. Since well water is groundwater, it is easy to see why pesticides must be kept out of groundwater.

Two undesirable processes that can remove pesticides from the target area are runoff and leaching. Runoff is the movement of pesticides in water across the soil surface. It occurs as water moves over a sloping surface, carrying pesticides either dissolved in the water or bound to eroding soil. The amount of pesticide runoff depends on the grade or slope of an area, the erodibility and texture of the soil, the soil moisture content, the amount and timing of irrigation or rainfall, and properties of the pesticide. Leaching of pesticides occurs as water moves downward through the soil. Factors that influence leaching include whether the pesticide dissolves easily in water, soil structure and texture, the amount and timing of irrigation or rainfall, the amount of adsorption to soil particles, and the persistence of the pesticide.

The table on the back of this page lists the potential for leaching or runoff for some common pesticides used on soybeans. (*The listing of these* products does not imply endorsement by the Cooperative Extension Service or bias against those not mentioned.) These runoff/leaching potential ratings are from the ARS/SCS pesticide properties database and were developed for use with the SCS soils ratings for water quality in the SCS Soil-Pesticide Interaction Rating. Runoff ratings are based on the pesticide's ability to bind to the sediment in runoff.

Soil and site information along with pesticide characteristics must be taken into account when assessing the potential risk of pesticide use on water quality. If the *site* has a high potential for surface runoff or leaching (sandy soils and other soil characteristics), choose a pesticide that has a low potential for runoff or leaching or use a non-chemical method for pest control.

#### Additional Precautions to Keep Pesticides Out of Surface and Groundwater

It is very difficult to clean contaminated surface and groundwater. The best solution is to prevent contamination in the first place. The following pesticide applicator practices can reduce the potential for surface and groundwater contamination.

- Use integrated pest management programs—Minimize pesticide use by combining chemical control with other pest management practices such as resistant varieties, cultural practices, crop rotation, biological control agents, etc.

- Consider the geology of your area—Be aware of the water table depth and the permeability of the geological layers between the surface soil and groundwater.

- Consider soil characteristics— Determine the susceptibility of the soil to leaching or runoff. - Select pesticides carefully— Pesticides that are highly soluble, relatively stable, and not readily adsorbed to soil are the most likely to leach.

- Follow label directions—The label carries crucial information about the proper rate, timing, and placement of the pesticide.

- Calibrate accurately—Equipment should be calibrated carefully and often to avoid over or under application.

- Measure accurately—Concentrates need to be carefully measured before they are placed into the spray tank. Do not "add a little extra" to ensure the pesticide will do a better job.

- Avoid back-siphoning—The end of the fill hose should remain above the water level in the spray tank at all times to prevent back-siphoning of the pesticide into the water supply. Use an anti-backflow device when siphoning water directly from a well, pond, or stream.

- Consider weather and irrigation—If you suspect heavy rain will occur, delay applying pesticides. Control the quantity of irrigation to minimize potential pesticide leaching and runoff.

- Avoid spills—But when they do occur, contain and clean them up quickly with an absorbent material like cat litter.

- Change the location of mixing areas—Mix and load pesticides on an impervious pad if possible. If mixing is done in the field, change the location of the mixing area regularly.

- Dispose of wastes properly— Obey laws regulating the disposal of pesticide wastes. Triple rinse containers. Pour the rinsewater into the spray tank for use in treating the site or the crop.

- Store and mix pesticides away from water sources such as wells, pond, and springs.



## **Common Soybean Pesticides** Potential for Leaching and Runoff

	-	Potential for Potential for	
Trade Name	Common Name	Leaching	Runoff
Herbicides			
Amiben	chloramben	high	low
Arena	alachlor	medium	medium
Assure	quizalofop	low	high
Basagran	bentazon	medium	low
Blazer	acifluorfen	medium	medium
Classic	chlorimuron-ethyl	low	low
Cobra	lactofen	none	medium
Command	clomazone	medium	medium
Dual	metolachlor	medium	medium
Fusilade 2000	fluazifop-P-butyl	low	high
Gramoxone Extra	paraquat	low	high
Hoelon	diclofop	none	medium
Lasso	alachlor	medium	medium
Lexone	metribuzin	high	medium
Linex	linuron	medium	medium
Lorox	linuron	medium	medium
Lorox Plus	linuron +	*	*
	chlorimuron-ethyl		
Option	fenoxaprop	none	high
Pinnacle	DPX-M6316	low	low
Poast	sethoxydim	low	low
Preview	metribuzin +	**	**
	chlorimuron-ethyl		
Prowl	pendimethalin	low	high
Pursuit	imazethapyr	high	low
Reflex	fomesafen	high	medium
Roundup	glyphosate	low	high
Scepter	imazaquin	high	low
Sencor	metribuzin	high	medium
Sonalan	ethalfluralin	low	high
Tackle	acifluorfen	medium	medium
Treflan	trifluralin	low	high

See Lorox and chlorimuron ethyl rankings

\*\* See Lexone and chlorimuron ethyl rankings

#### Insecticides

Ambush	permethrin	low	high
Asana XL	esfenvalerate	low	high
Cygon	dimethoate	medium	low
DeFend	dimethoate	medium	low
Guthion	azinphos methyl	low	high
Lannate	methomyl	high	medium
Larvin	thiodicarb	low	medium
Lorsban	chlorpyrifos	low	high
Malathion	malathion	low	low
Orthene	acephate	low	low
Pounce	permethrin	low	high
Savit or Sevin	carbaryl	low	medium

MSU is an Affirmative Action /Equal Opportunity Institution. Cooperative Extension Service Programs are open to all without regard to race, color, national origin, sex or handicap. Issued in furtherance of Cooperative Extension work in agriculture and home economics, acts of May 8, and June 30, 1914, in cooperation with the U.S. Department of Agriculture. J. Ray Gillespie, interim director, Cooperative Extension Service, Michigan State University, East Lansing, MI 48824. This information is for educational purposes only. Reference to commercial products or trade names does not imply endorsement by the Cooperative Extension Service or bias against those not mentioned. This bulletin becomes public property upon publication with credit to MSU. Reprinting cannot be used to endorse or advertise a commercial product or company. This material is based upon work supported by the U.S. Department of Agriculture, Extension Service, under special project number (89-EWQI-1-9142). 1M-5:90-TCM-UP-New. Price 30 cents. File 23.413 (Water Quality)

printed on recycled paper

0-18688